



## Produce Vacation Videos in Minutes With Roxio VideoWave

## Roxio Easy Media Creator 10

© 2007 Sonic Solutions. All rights reserved.

Roxio VideoWave has all the features necessary for long, highly creative projects, but it's also great for quickly producing short, simple videos, even if you're just learning to use the program. In this tutorial, I'll show you how I quickly combined some cool underwater shots into a 2-minute video I could email to friends, or upload to YouTube.	
<ul> <li>A. Customizing the VideoWave Interface</li> <li>Let's start by customizing the VideoWave Interface.</li> <li>1. Run Easy Media Creator 10 Suite, and click Video in the Project Pane.</li> </ul>	Video
<ul><li>2. Then click VideoWave.</li><li>The Welcome to VideoWave splash screen opens.</li></ul>	Video Video Guide Capture Video Plug & Burn™ CineMagic VideoWave MyDVD Spress MyD Click VideoWave Com
<ul> <li>3. Choose either a Normal (4:3) project, or a Widescreen (16:9) project, depending upon your source video.</li> <li>VideoWave opens.</li> </ul>	Welcome to VideoWave         • Create a new production:         Format       Normal (4:3)         Edit an exist       Normal (4:3)         Widescreen (16:9)       Widescreen (16:9)         Select Normal (4:3) or       Widescreen (16:9)

Interface tour: Let's take a quick Tour

On the left is the **Task Pane**, where you'll insert content like photos, video and audio into your projects, and then add text, video effects, transitions and the like.

On the bottom is the **Production Area**, which has two views, storyline and timeline. I'll explain how each works in a moment.

On top is the Preview Window, where you can watch videos, and add titles and customize effects.

See the open space to the right of the Preview Window? Let's dock two windows there to make my content and effects easier to access.





<ul><li>1b. Right click the target video clip, and choose Scene Detection.</li><li>VideoWave opens the Scene Detection window.</li></ul>	Preview Extract Image Extract Audio Scene Detection Right click and choose Scene Detection Lut Copy	
<ul> <li>1c. On the bottom left of the Scene Detection window:</li> <li>Set the Sensitivity level – Higher values increase sensitivity, producing more scenes. At 10, VideoWave detects only major scene changes, which is a good starting point.</li> <li>Click Auto-detect now to start detecting scenes.</li> </ul>	Auto-detect Auto-detect now Sensitivity: Set Sensitivity level	•

1d. VideoWave will start detecting scenes and inserting them into the preview window on the right.

- If VideoWave detects too many, or too few scenes, click **Stop Auto-detect**, adjust the Sensitivity slider and restart the process.
- After completing scene detection, click OK to insert the scenes into Media Selector's My Media tab.

Scene Detection				
	$\mathbb{D} \times \mathbb{Q}$	8		
AND AND BEREAS	00:06:04	:16 00:06:09:19	00:06:19:01	
	00:06:21	:13 00:07:03:08	00:07:13:18	
	*			
Add Click Stop Auto-detect Sensitivity: 10.00 - +	00:07:18	:19 00:07:27:16	00:07:39:10	
	00:08:08	:16	Click OK	
		C	OK Cancel	Help
2. Find your scenes. In the Media Selector tab	).	Media Selector	Effect Selector	
• Click the <b>My Media</b> tab to view the sce			Adjust	
• Adjust the size and number of scenes in window using the Adjust <b>Thumbnail S</b> slider.	the	Click the My Media tab	(	

## 3. Select and add your scenes to the Storyline:

- Add individual scenes by clicking and dragging them to the first panel in the Storyline.
- Add contiguous scenes by clicking the first scene, holding down the Shift key and clicking the last scene; then dragging all scenes to the first panel in the Storyline.
- Add random scenes by holding down the Ctrl key and clicking all desired scenes; then dragging all scenes to the first panel in the Storyline.

## 4. Sequence scenes in the Storyline.

- Each Storyline panel contains a scene, with the first frame displayed in the panel.
- You can play any scene by selecting it and clicking Play in the Preview Window.
- You can move scenes around like checkers on a board. To move a scene, **Click**, **drag and release** the scene in the target location. VideoWave will insert the scene, and move other scenes as necessary.



**5.** *Trim scenes in Storyline view*. One key to producing great home video is to keep each scene and the entire video as short as possible. Fortunately, VideoWave makes it fast and easy to trim unwanted frames from the beginning and end of each scene.

- To trim a scene, double click the Panel in the Storyline. VideoWave's Video Trimmer opens.
- Drag the **Green triangle** to the new first frame of the trimmed clip.
- Drag the **Red triangle** to the new last frame of the trimmed clip,
- Click OK. VideoWave trims the scene. Note that VideoWave is a "non-destructive" editor, so you're not actually deleting any frames the captured video file, just telling VideoWave not to include them in the final video.





7d. Here's the procedure for SmartSound.

- First, select a **Style/Library**, which are labeled in the common genres you can see below.
- Then, select a **Title**, which are different songs within that genre.
- Finally, choose a **Variation**, which are different variations of that song.
- At any point in the process, you can click **Preview**/ **Stop** to preview your audio.
- After selecting your music, enter the desired Duration into the duration fields, or check the **Auto Fit** checkbox so music duration will match project duration.
- Click **OK** to close the SmartSound Audio dialog, and Click **OK** to close the Background Audio dialog.

Media Selector	SmartSound®			
artSound®				
		nd variation. Click Preview to play the	selection. When you are done, click OK	to add the
artSound to your productio	Check Auto	. Duration [		
e: Music	Fit checkbox ] <sup>: Owne</sup>	d 🚽 Duration:	00 : 🔟 : 30 🚔 hh:mm:ss	
wse by: 💿 Style 🕕 Li	ibrary O Title Auto Fil	]		
		· .		
tyle/Library:	Title:	Variations:	Saved History:	
Blues	Jungle Games	Clearing	Jungle Games - Cleaving	
Classical	Kicl Back	Ritu		ick
Country/Folk	Select Title	Select	Pre	view
Eusion Eutur Vic	hie areae Escape		_	
<sup>Ja:</sup> Select		Summon		
<sup>-al</sup> Style/Library		Passage	<b>V</b>	
Wit	h a conce of four-hoding, this could	ious percussive track is on the lookout	from all Clearing is 00:00:29:20 in	longth.
	es. Great for medium suspense lev		from all Cleaning is 00:00:29:20 in	iengtn.
		Ċ.		
	SmartSound	N Duratika	OK	Cancel
	SmartSound	B Export to		Cancel





9b. After saving the project, VideoWave will open the Make Movie dialog. In this dialog:

- Click **Video File** to produce a video file.
- Click the **Purpose** list box to choose a target for your video file.
- Choose the **target**.
- Click Create Video File to start rendering.

Video File	DV Camera	TV or VCR	E-mail
-Purpose - Click the	Purpose list box		
TV/VCR Playback DVD Playback DivX DV Output VCD Playback General Editing Playback on another PC AVC (H.264) SVCD Playback E-Mail Slideshow All Normalize Audio	Choo	se the <b>target</b>	
File name			
C:\Documents and Settings\Ad	lministrator\My Documents\M	y Videos Click Cre Video F	Distance in the second s
	Preview	Create Video File	Close Help